


MS SQL Server and SSMS on Windows

This is a step-by-step guide for installing MS SQL Server (latest at the time of writing this document) and SSMS for Windows OS.

Download MS SQL Server for Windows


Click [here](#) to go to the SQL Server Downloads link. Scroll down and choose between the Developer edition or Express edition.

You need to choose **SQL Server 2022 Express edition**.




1. Click on the Download now button for the *SQL Server 2022 Express* edition.
2. Next, double click the .exe file from your installed location to start the installer.

3. Select the recommended **Basic installation type**.



4. Click Accept to accept the License Agreement.
5. You can select the default install location by clicking the next button.
6. Click Install.

7. One Installation is completed, you need to then click on **Install SSMS**.



Install SSMS

1. Click **Install SSMS**.
2. On the download page (<https://learn.microsoft.com/en-us/ssms/install/install>), scroll down and

click on **Download SQL Server Management Studio (SSMS)**.

🔗 Step 2 - Determine which version of SQL Server Management Studio to install

Decide which version of SSMS to install. The most common options are:

- The latest release of SQL Server Management Studio 21 that is hosted on Microsoft servers. To install this version, select the following link, which downloads a stub installer, or *bootstrapper*, to your *Downloads* folder.

[Download SSMS 21](#) 

- If you already have SQL Server Management Studio 21 installed, you can [install another version alongside it](#).


You can download a bootstrapper or installer for a specific version from the [Release history](#) page and use it to install another version of SSMS.

3. **Double click the SSMS-Setup-ENU.exe executable from your download location.**
4. **Click Install.**
5. **Once SSMS is successfully installed, click Restart.**

Congratulations! You have successfully installed MS SQL Server and SQL Server Management Studio (SSMS) 18.9.2 on Windows.

After Restarting your system. Search SSMS in the Search Bar and Click to open it.

- 1. After SSMS opens, it will ask for connection setup. Choose windows Authentication.**



2. For server name, Click on Browse and in local select your server name.

The screenshot shows the 'Connect (Preview)' dialog box. The 'Browse' tab is selected, displaying a tree view of server locations. Under 'Local', the server 'DESKTOP-2BKBH4I\SQLEXPRESS, <default>' is selected. Below the tree, the 'Connection Properties' section is visible, showing fields for Server Name, Authentication, User Name, Password, Database Name, and Encrypt. The 'Trust Server Certificate' checkbox is unchecked. At the bottom, there are 'Connect', 'Cancel', and 'Help' buttons.

Connect (Preview)

History **Browse**

Local

DESKTOP-2BKBH4I\SQLEXPRESS, <default>

Network

Azure

Registered Servers

Connection Properties Connection String

Server Name: DESKTOP-2BKBH4I\SQLEXPRESS

Authentication: Windows Authentication

User Name: DESKTOP-2BKBH4I\singh

Password:

☐ Remember Password

Database Name: <default>

Encrypt: Mandatory

☐ Trust Server Certificate

Advanced...

Custom Properties

Name:

Color: <default> Custom...

Connect Cancel Help

3. Then Click on Trust Server Certificate.

4. Then Click Connect.